## FORENSIC BIOLOGY PROTOCOLS FOR FORENSIC STR ANALYSIS

Amplification using the Power Plex Fusion System		
Status: Published		Document ID: 5980
DATE EFFECTIVE	APPROVED BY	PAGE
08/22/2022	Nuclear DNA Technical Leader	1 OF 3

# PowerPlex® Fusion Sample Preparation for Amplification

## 1 Procedure

Fusion Sample Input Amount	
Optimal – 525pg*	
Minimum – 37.5pg	

<sup>\*</sup>The option for amplification with a greater input amount is available if determined appropriate for the sample by the analyst.

1.1 Retrieve the following reagents from the associated refrigerator and/or freezer and record the lot numbers.

PowerPlex Fusion® 5X Primer Pair Mix	
PowerPlex Fusion® 5X Master Mix	
Water, Amplification Grade	
2800M Control DNA, .250ng/µl	

- 1.2 Retrieve sample(s) needed for amplification from associated refrigerator and/or freezer.
- 1.3 Prepare dilutions in 1.5 mL tubes according to the values listed on the test batch data entry screen or the "FBAmplificationSheet", <u>using Promega Amplification Grade Water</u>, for each sample, if necessary, according to Table 1. Vortex and centrifuge samples prior to aliquoting for dilution.

**TABLE 1: Dilutions** 

Dilution	Amount of DNA Template (uL)	Amount of Promega® Water (uL)
0.25	3 or (2)	9 or (6)
0.2	2	8
0.1	2	18
0.05	2	38
0.04	4 or (2)	96 or (48)
0.02	2 or (1)	98 or (49)
0.01	2	198
0.008	4 or (2)	496 or (248)

- 1.4 Label amp tubes using the values generated by LIMS. These values can be found in the test batch output samples or on the "FBAmplificationSheet".
- 1.5 Centrifuge reagent tubes briefly to bring contents to the bottom and then vortex for 15 seconds before use. Do NOT re-centrifuge the Master Mix or Primer Pair Mix as this may cause the reagents to be concentrated at the bottom of the tube.

Controlled versions of Department of Forensic Biology Manuals only exist in the Forensic Biology Qualtrax software. All printed versions are non-controlled copies.

## FORENSIC BIOLOGY PROTOCOLS FOR FORENSIC STR ANALYSIS

Amplification using the Power Plex Fusion System		
Status: Published		Document ID: 5980
DATE EFFECTIVE	APPROVED BY	PAGE
08/22/2022	Nuclear DNA Technical Leader	2 OF 3

1.6 Consult the Reagents tab in LIMS for the exact amount of PowerPlex Fusion® 5X Primer Pair Mix and PowerPlex Fusion® 5X Master Mix to add.

Reagent	Per reaction
5X Primer Pair Mix	2.5 μL
5X Master Mix	2.5 μL
Mastermix total:	5 μL
DNA	7.5 µL

- 1.7 Vortex prepared Master Mix and all samples to be aliquoted. After vortexing, **briefly centrifuge** master mix and samples.
- 1.8 Add  $5 \mu L$  of the prepared master mix to each tube that will be utilized, changing pipette tips and remixing master mix as needed.
- 1.9 **Witness Step.** Have another analyst witness the sample set-up.
  - 1.9.1 For the input samples, confirm the tube label and sample ID for each sample. For the output samples, the entire amp tube label must be read for each sample.
- 1.10 Positive Control total input amount of 375pg.
  - 1.10.1 Aliquot positive control according to amplification sheet
- 1.11 Amplification Negative
  - 1.11.1 7.5 uL of Water, Amplification Grade
- 1.12 Samples
  - 1.12.1 Aliquot samples according to amplification sheet
- 1.13 Ensure that all caps are properly closed prior to sending the samples to the post-amplification laboratory.
- 1.14 Spin down samples at 1000 RPM for one minute.
- 1.15 For thermal cycler usage see the Using the Mastercycler X50s manual..

## FORENSIC BIOLOGY PROTOCOLS FOR FORENSIC STR ANALYSIS

Amplification using the Power Plex Fusion System		
Status: Published		Document ID: 5980
DATE EFFECTIVE	APPROVED BY	PAGE
08/22/2022	Nuclear DNA Technical Leader	3 OF 3

1.16 The Fusion PCR program is as follows:

Soak at 96°C for 1 minute

: Denature at 94°C for 10 seconds

: Anneal at 59°C for 60 seconds 29 Cycles

: Extend at 72°C for 30 seconds

10-minute incubation at 60°C.

Storage soak indefinitely at 4°C

NOTE: The 4°C storage soak step is not meant to store samples for an extended period. Samples should be removed from the instrument and placed in the 4°C refrigerator at the earliest convenience.

1.17 Place the microtube rack used to set-up the samples for PCR in the container of 10% bleach container in the Post-Amp area.



Qualtrax template 072220